

THE GHR COIN WINDOWS TUTORIAL




Gaming-Hosting-Recharge

20
19

WELCOME

EASY WINDOWS TUTORIAL FOR LAUNCHING MN AND EARN THE PROFITS FROM GHR COIN



TUTORIAL

DOWNLOAD GHR COIN WALLET FROM [HERE](#)

MASTERNODE GUIDE

This guide is to help on how to setup GHR masternode on windows wallet.

REQUIREMENTS:


5,000 GHR

Windows running computer

A different IP address for EACH masternode


STEPS

1. Have a local wallet that is fully synced
2. Click on Tools, and then Debug console





3. You will find command line at bottom of the console



Enter the following **commands** and press **Enter**

masternode genkey

You will see a long string of numbers and strings

Copy/paste the string to the notepad file on your Desktop (Masternode Private Key)

This is the **genkey** you will need to use later in the process.

Enter the following command to generate your masternode **receiving address**

getaccountaddress MN1

The generated address will now be labeled as **MN1**

Please **copy/paste** this string to the notepad file on your Desktop label as address

This address will be the one that you will use to send your collateral, and the one where all future rewards will be received

If you want to setup **more masternodes** just repeat the steps so you end up with several addresses for the total number of nodes you wish to setup

Still on PC, open the *ghrcoin.conf* file by

MENU : *Tools - Open masternode Configuration file*

Make it look like this:

```
rpcuser=long random username  
rpcpassword=longer random password  
rpcallowip=127.0.0.1  
listen=1  
server=1  
daemon=1  
logtimestamps=1  
maxconnections=256  
masternode=1  
externalip=your unique public ip address  
masternodeprivkey=output of masternode genkey
```


Optional (recommended for security) :

Make sure to replace *rpcuser* & *rpcpassword* with your own inputs

Save, close and restart the wallet



7. Start your Masternode in GHR COIN Wallet



MENU : Masternodes

CLICK : **'Start Missing'** -OR- Select new Masternode and click **'Start Alias'**

You should see : **"MNx successfully started"**

TIP : Do not restart any masternodes you already have running or

you will reset the rewards and end up waiting for a long time to get paid again.

If you get stuck, have questions or you just want to meet cool **GHR COIN Community**, check out our [Discord](#) or [Telegram](#)



THANK YOU



GHR COIN
G A M I N G H O S T I N G R E C H A R G E

CONTACT US



Website



Facebook



E-mail:
support@ghrcoin.io



Discord



Reddit



Telegram



Designed by Shasha
shashaera101@gmail.com